

Complete list of CLI commands

| Command | Example | Description |
|------------------------|---|---|
| add user | add user alice 12345 | Add a user with the specified name and password |
| add app | add app MyApp MyAppKey 'http://localhost' | Add a new application |
| add app-rest-method | add app-rest-method MyAppKey connect | Add a new REST method to the application |
| add lb-node | add lb-node --http-port 8081 --flash 1935 --ws 8080 --wss 8443 --max-calls 999 --enabled true 192.168.1.5 | Add a node to the load balancer |
| add authorized_key | add authorized_key -f /root/.ssh/public.pem | Add public key for CLI authorization |
| grep | grep foo | Search strings using the specified template |
| passwd | passwd passwd alice | Change the password |
| reload node-settings | reload node-settings | Reload settings from the flashphoner.properties file |
| remove app | remove app MyApp | Remove the application with the specified key |
| remove app-rest-method | remove app-rest-method MyApp ErrorStatusEvent | Remove the REST method from the application |
| remove lb-node | remove lb-node 192.168.1.5 | Remove the node from the load balancer |
| remove authorized_key | remove authorized_key | Remove CLI authorization public key. This command switches public key authorization off. |
| save lb-nodes | save lb-nodes | Save nodes of the load balancer to a file |
| save node-settings | save node-settings | Save current server settings to the flashphoner.properties file |
| show groups | show groups | Show groups |
| show users | show users | Show users |
| show apps | show apps | Show the list of applications |
| show server-status | show server-status | Show the current server status |
| show app-status | show app-status MyApp | Show the current status of the specified application |
| show app-rest-methods | show app-rest-methods MyAppKey | Show the specified application REST methods |
| show streams | show streams | Show the list of active streams |
| show lb-nodes | show lb-nodes | Show nodes used in load balancing |
| show lb-status | show lb-status | Show the current status of the load balancer |
| show cdn-nodes | show cdn-nodes | Show the list and status of CDN nodes visible to the server (only for cdn_enable=true) |
| show cdn-routes | show cdn-routes | Show the list of CDN routes and streams CDN (only for cdn_enable=true) |
| show node-settings | show node-settings | Show or export the list of current WCS settings to a file (see Server settings management) |
| show node-setting | show node-setting http.address | Show a specific setting from the settings file |
| start lb | start lb | Start the load balancer |
| stop lb | stop lb | Stop the load balancer |
| update user | update user --active false alice | Modify the specified user data |

| | | |
|---------------------|--|---|
| update app | update app --c-class 'com.flashphoner.MyCallbackClass' --m-class 'com.flashphoner.MyMainClass' MyApp | Modify application settings m-class - main class handler. c-class - Callback class handler. |
| update lb-node | update --http-port 8081 --flash 1935 --ws 8080 --wss 8443 --max-calls 999 --enabled true lb-node 192.168.1.5 | Modify the load balancer settings |
| update node-setting | update node-setting --name http.address --value 127.0.0.1 | Modify the value of one option in the settings list |