

GCP load balancer with autoscale quick setup

- [Prepare server instances](#)
- [Create Edge disk image](#)
- [Create Edge instance template](#)
- [Create autoscaling group](#)
- [Create load balancer](#)
- [Load balancer testing](#)
- [Updating Edge servers settings](#)

WCS Google Cloud Platform instances support TCP Network load balancer.

WebSocket connections will be distributed between active load balancer instances. In case a scaling policy is executed (when the policy target – e.g., CPU load on instance - is reached) and new instances are launched, they will be added to the load balancer.

The following components would be required

- Disk image to use in instance template
- Instance template to create new server instances while autoscaling
- Autoscale instance group
- Load balancer
- Server health checks

Let's try to deploy CDN for WebRTC streams including one Origin server and a group of Edge servers (from 1 to 3 instances) with CPU load autoscaling.

Prepare server instances

1. Create one Origin and one Edge server as described [here](#). Reserve a static internal IP address to Origin server. Reserve external static IP address to use in load balancer

2. Configure CDN on Origin server side

```
cdn_enabled          = true
cdn_ip               = <origin_internal_ip>
cdn_role             = origin
cdn_nodes_resolve_ip = false
```

3. Configure CDN on Edge server side

```
cdn_enabled          = true
cdn_ip               = <edge_internal_ip>
cdn_point_of_entry   = <origin_internal_ip>
cdn_role             = edge
cdn_nodes_resolve_ip = false
```

4. Add the following parameter to Edge server settings

```
http_enable_root_redirect=false
```

5. Prepare and [import](#) SSL certificates to Origin and Edge servers. It is not recommended to use Let's Encrypt because it requires to update Edge disk image every 3 months.


Create Edge disk image

1. Stop Edge server instance

2. In Google Cloud console, go to "Compute Engine - Images" section and click "Create image". Choose Edge instance disk as disk image source and click "Create"

[←](#) Create an image

Name ?
Name is permanent

test-edge-image-1 

Source ?

Disk

Source disk ?

test-edge-1

Location ?

☒ Multi-regional

☐ Regional

eu (European Union) (default)

Family (Optional) ?

Description (Optional)

Labels ? (Optional)

+ Add label

Encryption

Data is encrypted automatically. Select an encryption key management solution.

☒ Google-managed key
No configuration required

☐ Customer-managed key
Manage via Google Cloud Key Management Service

☐ Customer-supplied key
Manage outside of Google Cloud

Your free trial credit will be used for this image. [GCP Free Tier](#) 

Create

Cancel

Equivalent [REST](#) or [command line](#)

Do not delete source Edge instance after disk image creation, it will be necessary for Edge disk image updating.

Create Edge instance template

1. Go to "Compute Engine - Instance templates" section and click "Create instance template". Choose instance VM configuration

Create an instance template

Describe a VM instance once and then use that template to create groups of identical instances [Learn more](#)

Name ?

Name is permanent

test-edge-template

Machine configuration

Machine family

General-purpose

Memory-optimized

Compute-optimized

Machine types for common workloads, optimized for cost and flexibility

Series

N1

Powered by Intel Skylake CPU platform or one of its predecessors

Machine type

n1-standard-1 (1 vCPU, 3.75 GB memory)

vCPU

1

Memory

3.75 GB

⌵ CPU platform and GPU

Container ?

☐

Deploy a container image to this VM instance. [Learn more](#)

2. In "Boot disk" section click "Change"

Boot disk ?

New 20 GB standard persistent disk

Image

test-edge-image-1

Change

On "Custom images" tab choose Edge disk image

Boot disk

Select an image to create a boot disk. The image determines the operating system installed on the instance. Can't find what you're looking for? Explore hundreds of VM solutions in [Marketplace](#).

Public images Custom images

Show images from

Test GCP LB

☐ Show deprecated images

Image

test-edge-image-1

Created on Jun 25, 2020, 1:53:31 PM

Boot disk type ?

Standard persistent disk

Size (GB) ?

20

3. On "Security" tab add the public SSH key if you do not have project SSH keys and click "Create"

Management
Security
Disks
Networking
Sole Tenancy

Shielded VM
Turn on all settings for the most secure configuration.

☐ Turn on Secure Boot
☒ Turn on vTPM
☒ Turn on Integrity Monitoring

SSH Keys
These keys allow access only to this instance, unlike project-wide SSH keys

☐ Block project-wide SSH keys
When checked, project-wide SSH keys cannot access this instance

gcp

gTaJ8gvi6x9RQB6niVuTN80cK3H1A4xINxQ29GGxWJ
wXe4kRKIkM4QnxUTsNNsC6yc/d57Ur773518Tevf3v
4GcWQ9gCPvoIIHZqE79zB0xbRhggjj4ED1rRbC11ug0
uGO+2kaChLkxHehJ+Xotz/NW0Az0cwkW1YSZGddiT
vICrIDvRXFD0nuSuj8EpBU3Jjj54zChTI2k4dUDcPY
kA/bAgy2tF5Ajc50ZCPIVcOu74R1/7RZ1YqgIJ1g+L
aB gcp

+

+ Add item

Less

You can always create instance templates free of charge. Your free trial credit won't be used.

Create
Cancel

Equivalent REST or command line

Create autoscaling group

1. Go to "Compute Engine - Instance groups" section and click "Create instance group". Choose instance group region and zone, select Edge instance template

Create an instance group

To create an instance group, select one of the options:

New managed instance group

A group of VMs created from a template.
Supports autohealing, autoscaling, auto updating, regional deployments, and load balancing.

New managed instance group for stateful workloads

A group of VMs created from a template, with preserved disks and metadata individually for each VM.
Supports autohealing, auto updating, regional deployments, and load balancing for stateful workloads.

New unmanaged instance group

A group of existing VMs that you manage.
Supports load balancing.

Organize VM instances in a group to manage them together. [Instance groups](#)

Name

Name is permanent

test-edge-instance-group

Description (Optional)

Location

To ensure higher availability, select a multiple zone location for an instance group. [Learn more](#)

☒ Single zone

☐ Multiple zones

Region

Region is permanent

europa-west3 (Frankfurt)

Zone

Zone is permanent

europa-west3-c

Specify port name mapping (Optional)

Instance template


test-edge-template

Number of instances

Based on autoscaling configuration

2. Choose "Autoscale" mode by "CPU utilization" metric, set metric target value to 80% and set maximum number of instances to 3

Autoscaling

Use autoscaling to allow automatic resizing of this instance group for periods of high and low load. [Autoscaling groups of instances](#) 

Autoscaling mode

Autoscale

Autoscaling metrics

Use metrics to determine when to autoscale the group.

[Autoscaling policy and target utilization](#) 

New metric

Metric type

CPU utilization

Target CPU utilization

80

%

Done

Cancel

+ Add new metric

Cool down period

Specify how long to wait for a new instance before taking its metrics into account.

[Cool down period](#) 

60

seconds

Minimum number of instances

1

Maximum number of instances

3

Scale In Controls

Prevent a sudden drop in the number of running VM instances in the group by controlling the process of scaling in. [Learn more](#)

☐ Enable Scale In Controls

Delete autoscaling configuration

3. Enable "Auto healing" and create a health check. Set TCP protocol, port 8081 and request /health-check

Create a health check

Health checking mechanisms determine whether VM instances respond properly to traffic. You cannot create a legacy health check using this page. For more information, refer to the [Health Checks Concepts](#) documentation.

Name

wcs-health-check



Description

WCS health checking



Scope



Global



Regional

Protocol

TCP



Port

8081



Proxy protocol

NONE



Request

/health-check



Response



Logs

Turning on Health check logs can increase costs in Stackdriver.



On



Off

Configure health criteria and click "Create" to return to group setup

Health criteria

Define how health is determined: how often to check, how long to wait for a response, and how many successful or failed attempts are decisive

Check interval

5

seconds



Timeout

5

seconds



Healthy threshold

2

consecutive successes



Unhealthy threshold

2

consecutive failures



You can create this health check free of charge

CREATE

CANCEL

Equivalent [REST](#) or [command line](#)

4. Expand "Advanced creation options" and enable "Do not retry machine creation", then click "Create"

Advanced creation options

Advanced configuration controlling how the instance group is created

☒ Do not retry machine creation.

If Compute Engine hits a usage limit or error during instance creation, then reduce the instance group size to create as many instances as possible.

[Hide advanced creation options](#)

Your free trial credit will be used for VM instances in this group. [GCP Free Tier](#)

Create

Cancel

Equivalent [REST](#) or [command line](#)

Autoscaling instance group will be created, and one instance will be launched

Instance groups CREATE INSTANCE GROUP REFRESH DELETE								
Instance groups are collections of VM instances that use load balancing and automated services, like autoscaling and autohealing. Learn more								
<div> <div>Filter resources</div> <div>Columns</div> </div>								
<input type="checkbox"/> Name ^	Zone	Instances	Template	Group type	Creation time	Recommendation	Autoscaling	In use by
<input type="checkbox"/> <input checked="" type="checkbox"/> test-edge-instance-group	europe-west3-c	1	test-edge-template	Managed	Jun 25, 2020, 2:09:10 PM		On: Target CPU utilization 80%	

Create load balancer

1. Go to "Network – Load balancers" section and click "Create load balancer". Choose "TCP Load Balancing"

←

Create a load balancer

HTTP(S) Load Balancing

Layer 7 load balancing for HTTP and HTTPS applications [Learn more](#)

Configure

HTTP LB
HTTPS LB (includes HTTP/2 LB)

Options

Internet-facing or internal
Single or multi-region

Start configuration

TCP Load Balancing

Layer 4 load balancing or proxy for applications that rely on TCP/SSL protocol [Learn more](#)

Configure

TCP LB
SSL Proxy
TCP Proxy

Options

Internet-facing or internal
Single or multi-region

Start configuration

UDP Load Balancing

Layer 4 load balancing for applications that rely on UDP protocol [Learn more](#)

Configure

UDP LB

Options

Internet-facing or internal
Single-region

Start configuration

2. Choose external load balancer "From internet to my VMs" and its region

←

Create a load balancer

Please answer a few questions to help us select the right load balancing type for your application

Internet facing or internal only

Do you want to load balance traffic from the Internet to your VMs or only between VMs in your network?

☒ From Internet to my VMs

☐ Only between my VMs

Multiple regions or single region

Do you want to place the backends for your load balancer in a single region or across multiple regions?

☐ Multiple regions (or not sure yet)

☒ Single region only

Continue

3. In "Backend configuration" section, on "Select existing instance groups" tab select Edge instance group and set session affinity to client IP and protocol

←

New TCP load balancer

Name ?
Name is permanent

test-lb

✓ Backend configuration
Your backend is configured

→

● Frontend configuration
You have not configured your frontend yet

i Review and finalize
Optional

Create

Cancel

Backend configuration

Name ?

test-lb

Region ?

europa-west3

Backends ?

Select existing instance groups

Select existing instances

test-edge-instance-group

No more instance groups available in this region

Backup pool ? (Optional)

None

Failover ratio ?

10

%

Health check ?

wcs-lb-health-check (HTTP)

port: 8081, timeout: 5s, check interval: 10s, unhealthy threshold: 3 attempts

Session affinity ?

Client IP and protocol

4. Choose "Create health check". Create server health check, set port 8081 and request /

Create a health check

Autohealing instance groups and load balancing use health checks to detect when an instance is unresponsive [Learn more](#)

Name ?

Name is permanent

wcs-lb-health-check

Description (Optional)

WCS health check for load balancer

Protocol

HTTP

Port ?

8081

Request path ?

/

⌵ [More](#)

Health criteria

Define how health is determined: how often to check, how long to wait for a response, and how many successful or failed attempts are decisive

Check interval ?

10

seconds

Timeout ?

5

seconds

Healthy threshold ?

2

consecutive successes

Unhealthy threshold ?

3

consecutive failures

Save and continue

Cancel

5. In "Frontend configuration" section create TCP port configurations for ports 8081, 8080, 8443, 8444 for HTTP(S) and WS(S). Set external static IP address to load balancer

←

New TCP load balancer

Name ⓘ
Name is permanent

test-lb

✓ Backend configuration
Your backend is configured

✓ Frontend configuration
Your frontend is configured →

ⓘ Review and finalize
Optional

CreateCancel

Frontend configuration

Specify an IP address, port and protocol. This IP address is the frontend IP for your clients requests.

New Frontend IP and port

⌵

Name (Optional) ⓘ
Name is permanent

test-lb-http

Add a description

Protocol
TCP

Network Service Tier ⓘ
☒ Premium (Current project-level tier, [change](#)) ⓘ
☐ Standard ⓘ

IP
test-lb-entry-point (34.107.5.128) ⌵

Port
8081

DoneCancel

+ Add Frontend IP and port

←

New TCP load balancer

Name ⓘ
Name is permanent

test-lb

✓ Backend configuration
Your backend is configured

✓ Frontend configuration
Your frontend is configured →

ⓘ Review and finalize
Optional

CreateCancel

Frontend configuration

Specify an IP address, port and protocol. This IP address is the frontend IP for your clients requests.

Protocol:TCP, IP:34.107.5.128, Port:8081	Not saved	✎
Protocol:TCP, IP:34.107.5.128, Port:8080	Not saved	✎
Protocol:TCP, IP:34.107.5.128, Port:8444	Not saved	✎
Protocol:TCP, IP:34.107.5.128, Port:8443	Not saved	✎

+ Add Frontend IP and port

You can add another port configurations (1935 for RTMP subscribers, 8082, 8445 for HLS etc depending on Edge use case)

6. Click "Create". Load balancer will start

Load balancing

[+ CREATE LOAD BALANCER](#) [REFRESH](#) [DELETE](#)

[Load balancers](#) [Backends](#) [Frontends](#)

Filter by name or protocol

<input type="checkbox"/>	Name	Protocol	Region	Backends
<input type="checkbox"/>	test-lb	TCP	europe-west3	1 target pool (1 instance)

To edit load balancing resources like forwarding rules and target proxies, go to the [advanced menu](#).

Load balancer testing

1. Go to Origin web interface and publish test stream in Two Way Streaming example
2. Go to Edge web interface using load balancer IP address. Play test stream in Player example

Flashphoner Web Call Server

Not secure | 35.234.93.218:8444/...

Demo

Security

License

v.0.5.28.2753-5.2.670-b27d96b2ac3023cd2206e22f94b47882f406005b

Stream

Streams

Player

Two-Way Streaming

Firewall

WebRTC

Stream

Stream

Stream

Stream

Screen

Embed

2 Player

Media

Video

Video


Screen

MCU

Confere

Two-way Streaming

Local




test

Stop

PUBLISHING

Player



4d49

Play

Available

wss://35.234.93.218:8443

Disconnect

ESTABLISHED

Flashphoner Web Call Server

Not secure | 34.107.5.128:8444/admin/de...

Demo

Security

License

v.0.5.28.2753-5.2.670-b27d96b2ac3023cd2206e22f94b47882f406005b

demo

Streaming

Streamers

Player

Two-Way Streaming

Firewall

WebRTC

Stream

Stream

Stream

Stream

Screen

Embed

2 Players

Media

Video


Video

Screen

MCU

Conferen

Player



WCS URL

wss://34.107.5.128:8443

Stream

test

Volume

Full Screen

PLAYING

Updating Edge servers settings

To update Edge servers settings, for example, to update SSL certificates, Edge disk image must be updated as follows:

1. Disable autoscaling and delete all Edge instances in Edge instance group

2. Launch source Edge server instance
3. Update the settings as needed (for example, update SSL certificates)
4. Stop source Edge instance
5. Delete Edge disk image
6. Create new Edge disk image with the same name (for example, test-edge-image-1)
7. Enable autoscaling in Edge instance group (autoscaling settings will be preserved)