

# Core settings

Server settings are stored in `/usr/local/FlashphonerWebCallServer/conf`. Main core settings are located in `/usr/local/FlashphonerWebCallServer/conf/flashphoner.properties` and `/usr/local/FlashphonerWebCallServer/conf/wcs-core.properties` files.

Gray color denotes outdated or not used settings files that were used in previous versions. These files will most likely be deleted in future updates of WCS.

| File                      | Description                                                                                                               |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------|
| account.xml               | Not used                                                                                                                  |
| cli/crash.properties      | Not used                                                                                                                  |
| cli/telnet.properties     | Not used                                                                                                                  |
| dtls-main-cert.pem        | DTLS certificate. By default, a self-signed certificate is used.                                                          |
| dtls-main-key.pem         | DTLS private key.                                                                                                         |
| flashphoner.properties    | WCS main config                                                                                                           |
| loadbalancing.xml         | Load balancer config                                                                                                      |
| log4j.properties          | Log4j logger config                                                                                                       |
| rtsp.auth                 | RTSP authentication config                                                                                                |
| token_keys.properties     | Private keys config to decrypt token                                                                                      |
| wss.jks                   | Certificate storage for Secure Websockets                                                                                 |
| callee.xml                | Not used                                                                                                                  |
| crossdomain.xml           | Config for cross-domain requests from Flash. Currently is not used, because all signal data go through Websockets.        |
| flashphoner.serverid      | ServerID for information                                                                                                  |
| loadtoolconfig.xml        | Not used                                                                                                                  |
| myflashphoner-ca          | Client certificate to query the license server <a href="https://my.flashphoner.com">my.flashphoner.com</a> :443 via HTTPS |
| WCS.version               | WCS version information                                                                                                   |
| wcs-core.properties       | Settings file to start the WCS server core                                                                                |
| flash_handler_publish.sdp | Description of SDP for streams published from a Flash client                                                              |
| flash_handler_play.sdp    | Description of SDP for streams played on a Flash client                                                                   |
| media_transponder.sdp     | Description of SDP for republishing of streams via RTMP on a third-party server                                           |
| rtmp_agent.sdp            | Description of SDP to capture streams via RTMP from a third-party server                                                  |
| rtsp_server.sdp           | Description of SDP used to playback streams published on server as RTSP                                                   |
| database.yml              | Core command line interface users and internal application settings file                                                  |